

Como ativar uma licença

- 1. Ativar a licença com conexão à Internet
- 2. Ativar a licença sem conexão com a Internet
- 1) Ativar a licença com conexão à Internet
- 1. Instalar o Softing LicenseManager V4 no computador que será licenciado: https://sensycal.com.br/wp-content/uploads/2024/08/licensemanager-v4-24.zip
- 2. Após a instalação, selecione a opção "Provide all PC-Id's" na aba "Configuration".

Softing License Manage	Settings		c
Licensing on Configuration Settings	Language Current language: en License activation server Proxy settings Software license search path C-Id's PC-Id's Provide all PC-Id's	Test server connection	
Settings			



3. Verifique se o Softing License Manager V4 pode se conectar ao servidor de licenças da Softing.

Softing License Manager	8
JORING Settings	C
Licensing on	
Current language: en fill in your Proxy settings	
Settings License activation server	
Software license search path	
License path	
PC-Id's Connection test	
☑ Provide all PC-Id's	
Lonenct to URL: http://www.softing.com/licensing/LicService/LicService.asmx HTTP state: attempt to connect to the host is in progress HTTP state: request has been sent; reading the server's response HTTP state: connection the host is open; neither sending a request, nor waiting the response HTTP request finished ; HTTP status code: 200 SUCCESSFULLY CONNECTED TO THE SERVER Connection test successfull	bra De
Copy to Clipboard	
Help Settings	

Verifique a conexão do gerenciador de licenças com o nosso servidor. Se o teste de conexão não for bem-sucedido, verifique as configurações de proxy. O status do teste de conexão deve ser 200 para ativar a licença.

Se não for possível configurar uma conexão, pule para a seção 2

4. Se o teste de conexão for bemsucedido, selecione o PC-Id desejado, que deve ser usado para o processo de ativação, digite a chave de licença e pressione "Activate license". Pronto, a licença estará ativada!





2) Ativar a licença sem conexão com a Internet

Siga estas etapas somente se o teste de conexão (1.1) não tiver sido bem-sucedido.

1. Exporte o PC-Id do computador que deve finalmente receber um arquivo de licença ativado

Softing License Manager		
Johing M	lanagement and activation of software licenses on PC's	C
R Licensing on	Available licenses on this PC	
	Product Name Order Number Version Expires Options License	
	dataFEED OPC Suite LRL-DY-134501 4.00 Local	
Softing Interface	License activation Activate for this PC Generate license file for remote PC PC with internet connection License Key: PC-Id: BIOS: innotek GmbH - VBOX - 1 (BIOS0	
	Activate license	
	PC without internet connection	
Configuration Help	Sy Export PC-lds Proof license file	

- 2. Instalar o Softing LicenseManager V4 em outro PC <u>com conexão à Internet</u>: <u>https://sensycal.com.br/wp-content/uploads/2024/08/licensemanager-v4-24.zip</u>
- 3. Verifique novamente a conexão com o servidor de licenças da Softing e a opção "Provide all PC-Id's" (Consulte 1.1 e 1.2).



4. Vá para a seção "Generate license file for remote PC" (Gerar arquivo de licença para PC remoto)

Softing License Manager		
rofting	Management and activation of software licenses on PC's	Importe o PC-Id remoto (consulte a etapa 2.1)
R Licensing on	Available licenses on this PC	Preencha a chave de
USB Dongle DSB Dongle Softing Interface	Product Name Order Number Version Expires Options License dataFEED OPC Suite LRL-DY-134501 4.00 Local License activation License activation Activate for this PC Generate license file for remote PC License Key: PC-Id: BIOS: Phoenix Technologies ITD - INTEL - 6040000 (BIOSVMware-423a8 1fc7c150fe1-d34e8ef5b4222c5d	licença válida, que foi enviada a você.
Configuration	Import PC-Id from remote PC The PCid of the PC where the license should be activate When the PCid and the license key filled in, then export the license file. Please import this .lic file on the other PC	

- 5. Clique em "Generate and export license file" (Gerar e exportar arquivo de licença) e salve-o.
- 6. Importar o arquivo com extensão **.lic** no PC que deve ser licenciado.

Itense Manager				optimize!
censing on Pc Pc VSB Dongle Use nearby the for the PC Use activation Cetwate for this PC Generate license file for remote PC Pc with internet connection License Key: Pc-1d: BIDS: innotek GmbH - VBOX - 1 BIDSD Pc without internet connection	ense Manager	nagement and activation of softw	are licenses on PC's	C
Product Name Order Number Product Name Order Number Version Expires USB Dongle Softing Interface Ucense activation Activate for this PC Generate license file for remote PC PC with internet connection License Key: PC-Id: BIDS: innotek GmbH - VBOX - 1 (BIDS) PC without internet connection License file PC without internet connection License file	nsing on	Available licenses on this PC		
VSB Dongle USB Dongle Softing Interface Ucense activation Activate for this PC Generate license file for remote PC PC with internet connection License Key: PC-Id: BIOS: innotek GmbH - VBOX - 1 BIOS0 PC-Id: BIOS: innotek GmbH - VBOX - 1 BIOS0 PC without internet connection License Key: License Key: License Key:		Product Name Order Number Version Expires O dataFEED OPC Suite LRL-DY-134501 4.00 <th>ptions License</th> <th></th>	ptions License	
Activate for this PC Generate license file for remote PC PC with internet connection Ucense Key: PC-Id: BIOS: innotek GmbH - VBOX - 1 (BIOSO PC without internet connection PC without internet connection Sector PC - Ids Import license file Infiguration	ISB Dongle	Jcense activation		
PC with internet connection Ucense Key: PC-Id: BIOS: innotek GmbH - VBOX - 1 BIOS0	ang Interface	Activate for this PC Generate license file for remote PC		
PC-Id: BIOS: innotek GmbH - VBOX - 1 (BIOS0 PC without internet connection Compared to the second		PC with internet connection		
PC without internet connection		PC-Id: BIOS: innotek GmbH - VBOX - 1 (BIOS0		
PC without internet connection		Activate li	cense	
nfiguration		PC without internet connection		
nfiguration		🍪 Export PC-Ids	Mart license file	
	iguration			
ala di seconda di s	guidton			

Se for bem- sucedido, o gerenciador de licenças deverá fornecer a licença como uma licença local.